

## Table of Contents

Our [DBAccess](#) supports a simple configurable connection pool with [ConnectionPoolProvider](#).

The ConnectionPoolProvider creates a default DataSource and an [IConnectionPool](#).

We currently use [Hikari](#) and [Tomcat](#) for our connection pool implementation. With Hikari we have an independent solution and Tomcat will only work on Tomcat application servers.

## Configuration

The connection pool can be enabled by simply calling `setConnectionPoolEnabled(true)` on DBAccess, or it can be enabled in [config.xml](#).

Example:

```
<application>
  ...
  <connectionpool enabled = "true"/>
  ...
</application>
```

We support different use-cases:

1. Implementing `getDataSource()` in application life cycle object (`Application.java`)
2. Configure specific `IDataSourceCreator` in `config.xml`, e.g.

```
  <connectionpool enabled = "true">
    <dataSourceCreatorClass>com.sibvisions.rad.persist.jdbc.datasource.TomcatDataSourceCreator</dataSourceCreatorClass>
  </connectionpool>
```

3. Configure ServiceLoader for `IDataSourceCreator`
4. Register custom `IDataSourceCreator` in `ConnectionPoolProvider`, e.g.  
`ConnectionPoolProvider.registerDataSourceCreator(CustomDataSourceCreator.class);`  
There are 2 `IDataSourceCreator` registered by default:  
\* `HikariDataSourceCreator`  
\* `TomcatDataSourceCreator`

The default implementations of `IDataSourceCreator` supports several parameter by default. The following example `config.xml` shows all supported parameters.

```
<application>
  ...
  <connectionpool enabled = "true">
    <!-- ----- General parameters ----- -->

    <!-- dataSourceCreatorClass is optional, HikaraDataSourceCreator or
        TomcatDataSourceCreator will be used by default depending on availability.
    <dataSourceCreatorClass>com.sibvisions.rad.persist.jdbc.datasource.TomcatDataSourceCreator</dataSourceCreatorClass> -->
    <!-- maxActive is optional, 80 will be used by default. -->
```

```
<maxActive>80</maxActive> -->
<!-- minIdle is optional, 10 will be used by default.
<minIdle>10</minIdle> -->
<!-- useAliveQuery is optional, true sets DBAccess.getAliveQuery(),
false is default, therefore either validationQuery or connection.isValid()
will be used.
<useAliveQuery>true</useAliveQuery> -->
<!-- validationQuery is optional, if it is not set, Hikari and Tomcat
pool uses connection.isValid().
<validationQuery>select 1</validationQuery> -->
<!-- validationQueryTimeout is optional, in seconds, if it is not set,
Hikari and Tomcat default values are used.
<validationQueryTimeout>3</validationQueryTimeout> -->

<!-- ---- Hikari specific parameters ---- -->

<!-- validationTimeout is optional, in milliseconds, if it is not set,
validationQueryTimeout or Hikari default value is used.
<validationTimeout>1000</validationTimeout> -->
<!-- keepaliveTime is optional, in milliseconds, if it is not set,
Hikari default value is used.
<keepaliveTime>1000</keepaliveTime> -->

<!-- ---- Tomcat specific parameters ---- -->

<!-- maxIdle is optional, if it is not set, minIdle is used.
<maxIdle>10</maxIdle> -->
<!-- initialSize is optional, if it is not set, minIdle is used.
<initialSize>10</initialSize> -->
<!-- testWhileIdle is optional, if it is not set, false is used.
<testWhileIdle>true</testWhileIdle> -->
<!-- testOnBorrow is optional, if it is not set, true is used.
<testOnBorrow>true</testOnBorrow> -->
<!-- testOnReturn is optional, if it is not set, false is used.
<testOnReturn>true</testOnReturn> -->
<!-- validationInterval is optional, in milliseconds, if it is not set,
Tomcat default value is used.
<validationInterval>3000</validationInterval> -->
<!-- timeBetweenEvictionRunsMillis is optional, in milliseconds, if it is
not set, Tomcat default value is used.
<timeBetweenEvictionRunsMillis>5000</timeBetweenEvictionRunsMillis> -->
<!-- minEvictableIdleTimeMillis is optional, in milliseconds, if it is
not set, Tomcat default value is used.
<minEvictableIdleTimeMillis>3000</minEvictableIdleTimeMillis> -->
<!-- removeAbandoned is optional, if it is not set, Tomcat default
value is used.
<removeAbandoned>true</removeAbandoned> -->
<!-- removeAbandonedTimeout is optional, in seconds, if it is not set,
Tomcat default value is used.
<removeAbandonedTimeout>3000</removeAbandonedTimeout> -->
```

```
</connectionpool>
...
</application>
```

From:

<https://doc.sibvisions.com/> - **Documentation**

Permanent link:

[https://doc.sibvisions.com/jvx/common/setup/connectin\\_pooling](https://doc.sibvisions.com/jvx/common/setup/connectin_pooling)

Last update: **2025/06/20 10:51**

